


# USB cable User Installation Manual v1.0


**For Windows win7**

( Dec/2009) J


- 1.Power on your computer and boot to Windows.
- 2.Locate the USB port of your computer and plug in the USB cable,and open Device Manager.  
Windows will detect the new device (USB–Serial Controller)
- 3.right click USB–Serial controller→Update Driver Software




- 4.select Browse my computer for driver software




5.select let me pick from a list of device drivers on my computer




6.Select the driver with the date of 7/31/2007 and click next to install




7. Windows will show a dialog box, select **Install this driver software anyway**



8. install successfully



## 9. Verifying the Installation



You should see the Prolific USB-to-Serial Comm Port (COM \*) device listing. This also means that Windows has assigned the device to COM \* port.